

Programmable ^{TI}**58/59**

Agriculture

Quick Reference Guide



TEXAS INSTRUMENTS
INCORPORATED
DALLAS, TEXAS

Printed in U.S.A.

1015755-102

CONTENTS

Calculating Notes	1
Conversions	2
Statistics	3
Special Control Operations	4
Alphanumeric Print Codes	5
Programming Notes	6
Memory Partitioning	7
Program Key Codes	8
Magnetic Cards (TI-59 Only)	9-10
Library User Instructions	11-

CALCULATING NOTES

Low Battery Indication

If the display flashes erratically, fades out, gives incorrect results or is inconsistent in any way, recharge the battery. Calculator operation can be resumed after several minutes of recharging.

Algebraic Hierarchy

Operations and functions are performed automatically in following order.

1. Math Functions (x^2 , cos, etc.)
2. Exponentiation (y^x) and Roots ($\sqrt[x]{y}$)
3. Multiplication, Division
4. Addition, Subtraction
5. Equals

Order applies to each set of parentheses. You can use up to 8 pending operations and 9 open parentheses, except where noted.

Flashing Display

A display flashing off and on indicates that an invalid key sequence has taken place or that the limits of the display have been exceeded. See Appendix B in *Personal Programming* for possible causes.

CONVERSIONS

Angle Formats

2nd **DMS** — **DEGREES, MINUTES, SECONDS TO DECIMAL DEGREES** — Converts an angle measured in degrees, minutes and seconds to its decimal degrees equivalent. **INV** **2nd** **DMS** reverses this conversion. Also used for time conversions. **Operates on display value only.** Submit 2 digits each for minutes and seconds. Entry and display format is DD.MMSSsss where DD is degrees, MM is minutes, SS is whole seconds and sss is fractional seconds.

Polar to Rectangular

R **x:|** **θ** **2nd** **P-R** → **y**; **x:|** → **x**

Rectangular to Polar

x **x:|** **y** **INV** **2nd** **P-R** → **θ**; **x:|** **R**

Only 4 pending operations are available for other uses when using D.MS or Polar/Rectangular conversions.

Angular Conversions

FROM \ TO	Degrees	Radians	Grads
Degrees		$\times \frac{\pi}{180}$	$\div 0.9$
Radians	$\times \frac{180}{\pi}$		$\times \frac{200}{\pi}$
Grads	$\times 0.9$	$\times \frac{\pi}{200}$	

STATISTICS

Initialize: **2nd** **Fix** **1** **SBR** **CLR**

Data Entry: x_i **x:|** y_i **2nd** **Σ+**

Data Entry Removal: x_i **x:|** y_i **INV** **2nd** **Σ+**

Trendline Data Entry: x_1 **x:|**, y_1 **2nd** **Σ+**, y_2 **2nd** **Σ+**, etc.

Trendline Point Removal: **x:|** **-** **1** **=** **x:|** y_i **INV** **2nd** **Σ+**

Calculations

Key Sequence

Mean of y-array then x-array	2nd Σ x:
Standard Deviation (N - 1 Weighting) of y-array then x-array (N Weighting) of y-array then x-array	INV 2nd Σ x: INV 2nd Σ 11 √ x: √
Variance (N Weighting) of y-array then x-array (N - 1 Weighting) of y-array then x-array	2nd Σ 11 x: 2nd Σ x² x: x²
Y-Intercept	2nd Σ 12
Slope after y-intercept	x:
Correlation Coefficient	2nd Σ 13
y' for new x	2nd Σ 14
x' for new y	2nd Σ 15

SPECIAL CONTROL OPERATIONS


Each special control operation is called by pressing **2nd** **00** **nn** where **nn** is the 2-digit code assigned to each operation (short form addressing can be used here). These operations use up to 4 pending operations and 1 sub-routine level.

Code nn	Function
00*	Initialize print register
01*	Alphanumerics for far left quarter of print column
02*	Alphanumerics for inside left quarter of print column
03*	Alphanumerics for inside right quarter of print column
04*	Alphanumerics for far right quarter of print column
05*	Print the contents of the print register
06*	Print last 4 characters of OP 04 with current display
07*	Plot ← in column 0-19 as specified by the display
08*	List the labels currently used in program memory
09	Bring specified library program into program memory
10	Apply signum function to display register value
11	Calculate variances
12	Calculate slope and intercept
13	Calculate correlation coefficient
14	Calculate new y prime (y') for an x in the display
15	Calculate new x prime (x') for a y in the display
16	Display current partition of memory storage area
17	Repartition memory storage area
18	If no error condition exists in a program, set flag 7
19	If an error condition exists in a program, set flag 7
20-29	Increment a data register 0-9 by 1
30-39	Decrement a data register 0-9 by 1

*Designed specifically for use with optional PC-100A Print Cradle

ALPHANUMERIC PRINT CODES

The first seven control operations allow you to create and print out alphanumeric messages. Twenty characters can be printed on each line. They are assembled and stored in groups of 5 characters at a time as shown below.



Each printed character is represented by a two-digit, row-column address code according to the following table:

	0	1	2	3	4	5	6	7
0		0	1	2	3	4	5	6
1	7	8	9	A	B	C	D	E
2	-	F	G	H	I	J	K	L
3	M	N	O	P	Q	R	S	T
4	.	U	V	W	X	Y	Z	+
5	×	*	√	π	e	<	>	,
6	↑	%	:	/	=	'	×	×
7	ε	?	÷	!	∏	∧	∏	Σ

For instance, A is code 13 and + is code 47

PROGRAMMING NOTES

Labels

Any key on the keyboard can be used as a label except **2nd**, **LRN**, **□**, **□**, **SST**, **BST**, **□** and the numbers 0-9.

DSZ

This instruction can be used with registers 0-9. Entry sequence is **2nd** **□** **X**, **N** or **nnn** where **X** is the data register used followed by the transfer address (label **N** or absolute address **nnn**).

Flags

Ten flags are available (0-9). Entry sequence for setting, resetting or testing flags is the flag instruction, flag number, then transfer address (testing only).

MEMORY PARTITIONING

Memory area is partitioned in sets of 10 registers where each register can hold a data value or 8 program instructions. To check placement of current partition, press **2nd** **□** **16**. To repartition, enter number of sets (**N**) of 10 data registers needed and press **2nd** **□** **17**.

N	Program/Data	
	TI-58	TI-59
N < 0 = N		
0	479/00	959/00
1	399/09	879/09
2	319/19	799/19
3	239/29*	719/29
4	159/39	639/39
5	079/49	559/49
6	000/59	479/59*
7	Flashing	399/69
8	Flashing	319/79
9	Flashing	239/89
10	Flashing	159/99
N > 10	Flashing	159/99

*Partition when calculator is turned on.

PROGRAM KEY CODES

Key Code	Key	Key Code	Key	Key Code	Key
00	0	39	EE	72*	STO
↓	↓	40	ED	73*	RCL
09	9	42	STO	74*	SUM
10	E	43	RCL	75	-
11	A	44	SUM	76	1/x
12	B	45	y ^x	77	x ^y
13	C	47	DE	78	Z+
14	D	48	Esc	79	π
15	E	49	Prn	80	Dr
16	I	50	EX	81	RST
17	F	52	EE	83*	GTO
18	G	53	(84*	Op
19	H	54)	85	+
20	CLR	55	+	86	St
22	INV	57	log	87	llg
23	Inx	58	ln	88	EMS
24	CE	59	int	89	π
25	CLR	60	log	90	Int
27	INV	61	GTO	91	R/S
28	log	62*	Prn	92*	INV
29	CP	63*	Esc	93	.
30	tan	64*	Prn	94	+/-
32	x ¹	65	X	95	=
33	x ²	66	Power	96	Write
34	√x	67	x ⁻¹	97	Dr
35	1/x	68	log	98	Ar
36	Prn	69	Op	99	Pr
37	P-R	70	Rd		
38	Off	71	SBR		

*Merged codes

RECORDING MAGNETIC CARDS (TI-59 Only)

Display When Write Pressed, Card Entered	Calculator Response
1, 2, 3, 4	Writes a card side with this number from the bank of this number (program and/or data) and records current partition on card.
-1, -2, -3, -4	Writes and protects card side with this number from the bank with this number. Also records current partition on card.
Any other number	Card is passed but not recorded. Rightmost two integer digits of display are flashed.

If the display is flashing any value when trying to read or record a card, the card is passed but not read or recorded and the rightmost two integers in the display are flashed.

The calculator should be in standard display format when reading or recording cards.

Only the integer portion of the display is recognized, i.e., 1.234 = 1.

READING MAGNETIC CARDS (TI-59 Only)

Display When Card Entered	Calculator Response
0	<p>Reads information into bank number listed on card if current partition matches that on card.</p> <p>If partition incorrect, card is passed, but not read — display flashes card side passed.</p>
1, 2, 3, 4	<p>Expects card with this side number to be read — displays that side number.</p> <p>If another side is entered or if partition is incorrect, card is passed but not read — display flashes card side passed.</p>
-1, -2, -3, -4	<p>Forces side to be read into this bank number regardless of the partition or the number on the card.</p> <p>A protected program cannot be forced into any bank or alternate partition.</p>
Any other number	<p>Card is passed but not read — rightmost two integers in display flash.</p>

LIBRARY USER INSTRUCTIONS

The remainder of this booklet contains the User Instructions for each program of the library.

REMOVING AND INSTALLING MODULES.

The library module can easily be removed or replaced with another. It is a good idea to leave the module in place in the calculator except when replacing it with another module. Be sure to follow these instructions when you need to remove or replace a module.

CAUTION

Be sure to touch some metal object before handling a module to prevent possible damage by static electricity.

1. Turn the calculator OFF. Loading or unloading the module with the calculator ON may cause the keyboard or display to lock out. Also, shorting the contacts can damage the module or calculator.
2. Slide out the small panel covering the module compartment at the bottom of the back of the calculator.
3. Remove the module. You may turn the calculator over and let the module fall out into your hand.
4. Insert the module, notched end first with the labeled side up into the compartment. The module should slip into place effortlessly.
5. Replace the cover panel, securing the module against the contacts.


AGRICULTURE LIBRARY DIAGNOSTIC

FM-01

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	DIAGNOSTIC MODULE CHECK Select program Run diagnostic		[2nd] [Pgm] 01	12. * * *
2			[SBR] [=]	
1	LINEAR REGRESSION INITIALIZATION Select program Initialize linear regression		[2nd] [Pgm] 01	0.
2			[SBR] [CLR]	

*These values are printed automatically if a print cradle is connected.

**A flashing number indicates a malfunction; check *Personal Programming* for an explanation of procedure to follow.



DIVISION OF EXTENSION AND EDUCATION

45-23

DATA STORAGE AND RETRIEVAL

FM-02

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Select program			
2a	Enter first data value	value	[2nd] [Pgm] 02	
2b	Enter next data value Repeat this step for each data value to be stored	value	[A] [R/S]	2. next memory #
3a	If the values are to be stored in data registers other than those beginning with 01 Enter memory register number for the first data value	number	[STO] 00	number
3b	Enter data value to be stored	value	[2nd] [A']	number + 1
3c	Enter next data value	value	[R/S]	next memory #
4a	TO OBTAIN A LIST OF VALUES If a print cradle is used Enter memory number for first value stored	memory #	[INV] [2nd] [List]	

4b	End the listing If no printer is used and the first memory register is 01		[R/S] [CLR] [B]	memory # 1. pause first value next memory # pause next value
4c	Repeat this step until all memory registers are checked If a printer is not being used and the first memory register is not 01 Enter register number of first value		[R/S]	
5a		memory #	[STO] 00 [2nd] [B']	memory # pause first value next memory # pause next value
5b	Repeat this step until all memory registers are checked		[R/S]	
6	Correct an entry	correct value	[STO] memory #	correct value
7	Remove the fixed decimal		[INV] [2nd] [Fix]	

METRIC CONVERSIONS

FM-03

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Select program Conversion of Weight—Kilograms and Pounds		[2nd] [Pgm] 03	
2	Enter weight in kilograms	weight in kg	[A]	weight in lb
3	Enter weight in pounds	weight in lb	[2nd] [A']	weight in kg
4	Conversion of temperature— Centigrade and Fahrenheit		[B]	°F
5	Enter temperature in Centigrade Enter temperature in Fahrenheit	°C °F	[2nd] [B']	°C

BATCH MIX

FM-04

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Select program		[2nd] [Pgm] 04	1st ingredient
2	Enter percent or amount of first ingredient	1st ingredient	[STO] 01	
3	Enter second ingredient	2nd ingredient	[STO] 02	2nd ingredient
4	Continue entering ingredients	ingredient	[STO] memory #	ingredient
5	Enter total pounds or percent of ingredients in lb or % formula	lb or %	[A]	lb or %
6	Enter total batch desired		[B]	1.**
7			[R/S]	amount of 1st ingredient*
8	Repeat this step for all ingredients		[R/S]	2.** amount of 2nd ingredient* ingredient number** amount of ingredient*

*These values are printed automatically if the calculator is connected to a print cradle.

**Value is displayed for approximately one-half second.

BEEF COW RATION ANALYZER

FM-05

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Select program If cows are in the last six months of pregnancy		[2nd] [Pg m] 05	
2	Enter average weight of pregnant cows Enter 0 if in middle three months of pregnancy or Enter 1 if in the last three months of pregnancy If cows are nursing calves or in the first three months of pregnancy Enter average weight of cows nursing calves Enter milking ability of cow average milker (10-18 lb daily)=1 superior milker (over 18 lb)=2 Enter feedstuffs	wt 0 1 wt 1 or 2	[A] [R/S] [R/S] [2nd] [A'] [R/S] [2nd] [B']	0.00 1.00 1.00 1.00 1.00
3				

4	Enter the following items for each feedstuff: cost/unit pounds/unit pounds fed/day percent dry matter percent crude protein percent TDN percent calcium percent phosphorus Repeat this step for additional feedstuffs	cost/unit lb/unit lb/day % dry matter % CP % TDN % Ca % P	[R/S] [R/S] [R/S] [R/S] [R/S] [R/S] [R/S] [R/S] [R/S]	2.00 3.00 4.00 5.00 6.00 7.00 8.00 1.00
5	Enter the number of cow days the ration provides	number	[B]	DM ^a (dry-matter intake) ratio ^a
6	Calculate the consumption ratio		[R/S]	TDN consumption ^a
7	Calculate the TDN consumption		[C]	ratio ^{a,b}
8	Calculate the TDN ratio		[R/S]	CP ^a
9	Calculate crude protein consumed		[D]	CP ratio ^{a,b}
10	Calculate crude protein ratio		[R/S]	lb of CP supplement ^a
11	Enter percent crude protein in ratio		[CLR] [2nd] [D']	CP supp for herd ^a
12	Calculate how much crude protein is needed for the entire herd	% CP	[R/S]	

13	Calculate calcium consumption	[E]	Ca ^{a,b}
14	Calculate how much the ration is long or short in Ca	[R/S]	Ca in ration ^{a,b}
15	Calculate phosphorus consumption	[R/S]	p ^{a,b}
16	Calculate how much the ration is long or short in P	[R/S]	P in ration ^{a,b}
17	Calculate the ration cost per cow	[2nd] [E']	cost/cow ^a
18	Alter ration by adding or subtracting and begin with step 4 to incorporate ration adjustment		

^a These values are automatically printed if a print cradle is connected.

^b A flashing display indicates that the ration is deficient.

FEEDLOT RATION ANALYZER

FM-06

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Select program		[2nd] [Pg] 06	
2	Enter animal weight	wt*	[A]	1.00
3	Enter price per unit of feedstuff	price*	[R/S]	2.00
4	Enter pounds per price unit of the feedstuff	lb*	[R/S]	3.00
5	Enter on as-fed basis pounds per day on a per head or on a per lot basis	lb*	[R/S]	4.00
6	Enter the dry-matter fraction of feedstuff	fraction*	[R/S]	5.00
7	Enter the net energy value for maintenance (NEM)	mcal/lb*	[R/S]	6.00
8	Enter the net energy value for gain (NEg)	mcal/lb*	[R/S]	7.00
9	Enter the metabolizable protein value	protein value*	[R/S]	8.00
10	Enter the urea-fermentation potential (UFP) value	UFP value*	[R/S]	9.00
11	Enter percent calcium for the feedstuff	% Ca*	[R/S]	10.00

12	Enter percent phosphorus	% P*	[R/S]	1.00
	Repeat steps 3 through 12 for additional feedstuffs			
13	Enter the number of animals that consumed the feedstuff	N*	[B]	consumption ratio
14	Calculate the pounds of dry matter per head		[R/S]	lb consumed per head*
15	Calculate average daily gain in lb		[C]	Steers-ADG (average daily gain)* Heifers-ADG*
16	Calculate feed cost per lb of gain	cost	[2nd] [C']	cost/lb
17	Enter non-feed cost per head	lb	[R/S]	total cost/lb
18	Enter lb of prot supp (supplemental protein) fed per day	0	[D]	4.00
19	If no supplement was fed, enter 0 Enter dry-matter fraction of protein supplement	fraction	[R/S]	4.00 7.00
20	Enter metabolizable protein value of protein supplement	protein value	[R/S]	8.00
21	Enter urea-fermentation potential value	UFP value	[R/S]	lb of supplement needed per head lb of supplement per lot
22	If supplement entered on a lot basis, calculate supplementation on a lot basis		[R/S]	

23	Repeat step 18 through 21 for different protein supplements Determine type of supplement needed positive = non-protein nitrogen supplements negative = natural protein supplement		[E]	positive or negative
24	Calculates surplus or deficiency of calcium in lb per head		[2nd] [D']	Ca deficiency or surplus**
25	Calculate surplus or deficiency of phosphorus		[R/S]	P deficiency or surplus**
26	Calculate the calcium to phosphorus ratio		[R/S]	Calcium to phosphorus ratio
27	Enter % calcium in Min Supp (mineral supplement) Enter % phosphorus in Min Supp	% Ca % P	[2nd] [E'] [R/S] [R/S]	10.00 lb of Min Supp amt of supp per lot
28	If feedstuffs entered on a lot basis, calculate amount of supplement needed per lot			

*These values are automatically printed if a print cradle is connected.

** A flashing negative number indicates a deficiency.

MP AND UFP DETERMINATION

FM-07

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Select program		[2nd] [Pgm] 07	
	PART A			
2	Enter percent crude protein	%	[A]	%
3	Enter percent TDN	%	[B]	%
4	Enter percent crude protein degraded	%	[C]	%
5	Calculate grams of metabolizable protein per lb or Calculate grams of metabolizable protein per kg		[2nd] [D']	metabolizable protein/lb metabolizable protein/kg
6	Calculate grams of urea		[R/S]	urea
	PART B			
2	Enter percent crude protein	%	[A]	%
3	Enter percent crude protein from NPN	%	[E]	%
4	Calculate grams of urea		[R/S]	urea

DAIRY RATION BALANCER

FM-08

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Select program		[2nd] [Pgm] 08	
	RATION BALANCER			
2a	Enter body weight	weight (lb)	[A]	weight*
2b	Enter daily milk weight	weight (lb)	[R/S]	weight*
2c	Enter milk fat test	%	[R/S]	%*
2d	Enter age of cow in years	age	[R/S]	age*
3	Enter forage data		[B]	1.
3a	Enter price per unit	price*	[R/S]	2.
3b	Enter weight per unit	weight* (lb)	[R/S]	3.
3c	Enter as-fed forage per animal	as-fed forage*	[R/S]	4.
3d	Enter forage DM fraction	DM fraction*	[R/S]	5.
3e	Enter NEL value (DM basis)	NE _L * (mcal/lb)	[R/S]	6.
3f	Enter percent CP (DM basis)	%*	[R/S]	7.
3g	Enter percent Ca (DM basis)	%*	[R/S]	8.
3h	Enter percent P (DM basis)	%*	[R/S]	1.
3i	Repeat 3a through 3h for any additional forages offered			

- 4a Calculate amount and composition of grain mixture (89% DM basis)
- 4b Calculate fraction of total DM intake
- 4c Calculate percent CP
- 4d Calculate percent Ca
- 4e Calculate percent P
- 5 Calculate expected DM intake
- 5a Calculate intake as percent of body weight
- 5b Enter a number above 1 to increase DM intake or a number below 1 to decrease it
Repeat step 4
- Optional:**
Add new forages to original forages
Repeat set 3a-3i

[C]

[R/S]

[R/S]

[R/S]

[R/S]

[2nd] [C']

[R/S]

[R/S]

[2nd] [B']

milk production level*

DM intake* **

amount of grain mixture* ***

fraction of total DM intake

% CP*

% Ca

% P

Expected daily DM intake

%

number

1.

- Optional:**
Change reference cow data if desired
- Repeat step 2a-2d
- 6a Enter lb of daily milk production
- 6b Calculate amount of 44% CP supplement
- 6c Calculate additional production levels in increments of 10 lb
- Calculate amount of 44% CP supplement
- Step 7 must follow either step 4 or step 6**
- 7a Calculate total daily DM intake
- 7b Calculate intake of as-fed forage
- 7c Calculate percent of as-fed forage in total ration
- 7d Calculate total forage cost

[A]

[D]

[2nd] [D']

[R/S]

[2nd] [D']

[E]

[R/S]

[R/S]

[2nd] [E']

weight*

DM intake* **

amount of grain mixture*

amount of supplement

level* **

DM intake* **

amount of grain mixture*

amount of supplement

DM intake intake

%

cost

PROTEIN TOP-DRESSING SCHEDULE

- 1a Enter CP percentage of grain mixture available
- 1b Calculate grain mixture and 44% CP supplement as in step 6 of Ration Balancer

RATION ANALYZER

- 1 Enter reference cow data as in step 2 of Ration Balancer
- 2 Enter forages and grain mixture as in step 3 of Ration Balancer
- 3a Evaluate ration -- energy content

If grain mixture is greater than 0, go to 3b

- Enter 1
- Generate number greater than 0
- Store number
- Calculate percent CP in 1 lb of supplement
- Calculate percent Ca

	%	[STO] 20	%
		[C]	expected DM intake*** amount of additional grain*
	1	[STO] 00 [R/S] [STO] 02 [R/S] [R/S]	1 number > 0 % Cp* % Ca

- Calculate percent P
- Calculate amount of 44% CP supplement

- 3b Follow the same procedures as in step 4, part b, of Ration Balancer

	[R/S] [C]	[2nd] [D']	% P Milk production** expected DM intake*** 0.0 amount of 44% CP supplement
--	----------------	--------------	-----------------------------------------------------------------------------------------

*These values are automatically printed when print cradle is attached.

**Value is displayed for approximately one-half second.

***Continuously flashing amount indicates that the amount is above 65% of the expected DM intake.

SWINE AND POULTRY RATION FORMULATION

FM-09

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Enter percent protein for feedstuff 1	%	[STO] 01	%
2	Enter and store percent nutrient for remaining nutrients in feedstuff 1, respectively	%	[STO] memory register number	%
3	Enter and store nutrients of feedstuff 2, respectively	%	[STO] memory register number	%
4	Continue for feedstuffs 3, 4, and 5	%	[STO] memory register number	%
5	Optional: Store values on magnetic card ¹	4	[2nd] [Write]	4
6	To read values, turn calculator on, enter 4, and insert magnetic card	4	[2nd] [Pgm] 09	0
7	Select program		[2nd] [E ']	639.390
	Initialize		[C]	3.000
8	Enter percent of feedstuff 3 in formula	%	[R/S]	4.000
9	Enter percent of feedstuff 4	%	[R/S]	5.000
10	Enter percent of feedstuff 5	%	[R/S]	0.000

11	Enter percent of protein or percent of lysine	%	[A]	% of feedstuff 1 required*
12	Calculate percent of feedstuff 2		[R/S]	% of feedstuff 2*
13	Calculate percent of protein in finished feed		[R/S]	% of protein*
14	Calculate percent of lysine		[R/S]	% of lysine*
15	Calculate percent of third, fourth, and fifth nutrient, respectively		[R/S]	% of third nutrient*
			[R/S]	% of fourth nutrient*
			[R/S]	% of fifth nutrient*
16	Enter quantity of batch	quantity*	[E]	amount of feedstuff 1*
			[R/S]	amount of feedstuff 2*
			[R/S]	amount of feedstuff 3*
			[R/S]	amount of feedstuff 4*
			[R/S]	amount of feedstuff 5*
17	To formulate new ration, repeat from step 8			
	Optional Procedure for High Moisture Content			
18	Enter percent of dry matter in feedstuff 1	%*	[D]	% of feedstuff 1 calculated on wet basis*

SWINE AND POULTRY RATION ANALYSIS

FM-10

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Select program		[2nd] [Pg] 10	0.
2	Initialize		[2nd] [E']	0.00
3	Enter the pounds of first ingredient	lb*	[A]	1.00
4	Enter the percent or amount per unit of weight of the first nutrient in feedstuff 1	% or amount	[R/S]	2.00
5	Enter percent or amount of second nutrient	% or amount	[R/S]	3.00
6	Enter percent or amount of third nutrient	% or amount	[R/S]	4.00
7	Enter percent or amount of fourth nutrient	% or amount	[R/S]	5.00
8	Enter percent or amount of fifth nutrient	% or amount	[R/S]	6.00
9	Enter percent or amount of sixth nutrient	% or amount	[R/S]	7.00
10	Enter percent or amount of seventh nutrient	% or amount	[R/S]	0.

11	Repeat steps 3 through 10 for as many feedstuffs as are called for in the formula		[B]	ration comp.*
12	Calculate the total weight of ingredients entered		[R/S]	analysis
13	Calculate average analysis for the first nutrient		[R/S]	analysis
14	Calculate average analysis for the second nutrient		[R/S]	analysis
15	Calculate average analysis for the third to seventh nutrients by repeating step 14		[R/S]	analysis

RELATIVE VALUE OF VARIOUS FEEDS FOR SWINE

FM-11

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Select program		[2nd] [Pgm] 11	
2	Initialize		[2nd] [E']	1.00
3	Enter price of corn	price*	[R/S]	2.00
3	Enter price of 44% protein soybean meal	price*	[R/S]	3.00
4	Enter price of dicalcium phosphate	price*	[R/S]	0.00
5	Calculate l-lysine value		[C]	l-lysine*
6	Calculate fat value		[D]	fat*
7	Calculate value of various feeds		[A]	1.
7	Enter metabolizable energy (kcal/lb)	kcal/lb	[R/S]	2.
8	Enter percent lysine	%	[R/S]	3.
9	Enter percent phosphorus	%	[R/S]	\$/cwt*
10	Calculate values of a second feed-stuff by repeating steps 7, 8, and 9			
	Optional procedure for TI-59			
1	Initialize		[2nd] [E']	1.

2	Assign identification numbers beginning with 10			
3	Assign register numbers: energy stored in 3 X identification number lysine stored in energy register + 1 phosphorus stored in energy register + 2			
4	Store values in registers using manual manipulation or FM-02	ME ly P	[STO] 30 [STO] 31 [STO] 32	ME ly P 0.
5	Record values on magnetic card		[CLR] [INV]	
	Enter 2 and insert magnetic card	2	[2nd] [Fix]	2.
	Enter 3 and insert second side of magnetic card	3	[2nd] [Write]	3.
	Retrieve values by entering identification number	ID	[2nd] [Write] [B]	value*

*These values are automatically printed if a print cradle is connected.

GESTATION MANAGEMENT

FM-12

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Select program		[2nd] [PgM] 12	
2	Enter days gestation	days	[STO] 00	days
3	Enter number of days from breeding for first management practice	days	[STO] 01	days
	If practice occurs before breeding			
	Enter number of days from breeding	days	[+/-] [STO] 01	days
4	Enter number of days from breeding for management practices	days	[STO] 02	days
		days	[STO] 03	days
		days	[STO] 04	days
		days	[STO] 05	days
5	Enter number of days from birth for first management practice			
	If practice occurs before birth			
	Enter number of days from birth	days	[+/-] [STO] 05	days
		days	[STO] 06	days
		days	[STO] 07	days
		days	[STO] 08	days

7	Enter breeding date	month,day*	[A]	DOB* (date of birth)
8	Calculate dates for management practices from breeding		[B]	date 1*
			[C]	date 2*
			[D]	date 3*
			[E]	date 4*
9	Enter DOB	DOB*	[2nd] [A']	BRED* (breeding date)
10	Calculate dates for management practices from birth		[2nd] [B']	date 5*
			[2nd] [C']	date 6*
			[2nd] [D']	date 7*
			[2nd] [E']	date 8*

*These values are automatically printed when a print cradle is connected.

BEEF WEANING AND YEARLING WEIGHT ADJUSTMENT FM-13

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	BEEF WEANING Select program		[2nd] [Pgm] 13	
2	Clear memories		[2nd] [CMs]	1.00
3	Initialize Enter standard birth weights for male and female calves	male standard birth weight female standard birth weight	[2nd] [E'] [R/S]	2.00 3.00
4	or Enter zeros for birth weight if you will be providing the birth weights	0	[R/S]	2.00
5	Enter the weaning date Enter one of the lists of age-of-dam factors from Table 1 in appropriate memories (mm) Repeat this step until all data is entered	0 date data	[R/S] [R/S] [R/S] [STO] mm	3.00 day of the year data
6	Enter the calf sex code (bull = 1, steer = 2, heifer = 3)	calf sex	[A]	calf sex
7	Enter calf's birth date	DOB (date of birth)	[B]	age in days

8	Enter age of dam in years	cow age	[C]	cow age
9	Enter the calf's birth weight if you will be providing it	birth weight	[D]	birth weight
10	Enter calf's actual weaning weight	weight	[E]	adjusted 205-day wt
11	Determine sex-adjusted 205-day weight		[R/S]	sex-adjusted 205-day weight
12	Repeat any or all of steps 6 through 11 for the next calf			
1	YEARLING WEIGHTS Select program		[2nd] [Pgm] 13	
2	Initialize		[2nd] [E']	1.00
3	Enter the date which calves started on test	date	[R/S]	2.00
4	Enter the date on which the yearling weight was taken	date	[R/S]	3.00
5	Enter the cattle's birth date	DOB	[R/S]	day of the year
6	Enter the weight at the start of the gain test	starting weight	[2nd] [A'] [2nd] [B']	number of days animal was on test age in days starting weight

7	Enter the cattle's adjusted 205-day weight	205 a. wt	[2nd] [C']	205 a. wt
8	Enter the cattle's actual yearling weight	yearling weight	[2nd] [D']	WDA (weight per day of age)
9	Calculate ADG (average daily gain)		[R/S]	ADG
10	Calculate cattle's adjusted 365-day weight		[R/S]	adjusted 365-day weight
11	Repeat any or all of steps 5 through 8 and follow step 8 with 9 and 10 for the next cattle			

PRODUCTION WORK SHEET

FM-14

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Clear memories		[2nd] [CMs]	0.
2	Select program		[2nd] [Pgm] 02	0.
	Enter the following data:		[A]	2.
	annual interest rate (divide by 2 for feeder-pig production; adjust for time required to complete production cycle for farrow-to-finish production)	rate		3.
	labor cost	cost	[R/S]	4.
	vet, medical, and operating costs	costs	[R/S]	5.
	marketing cost	cost	[R/S]	6.
	breeding stock investment (per litter for feeder-pig and farrow-to-finish production)	investment	[R/S]	7.
	depreciation per animal	depreciation	[R/S]	8.
	depreciation, interest, tax, insurance on equipment and buildings	depreciation	[R/S]	9.
	death rate as percent of animal	death rate	[R/S]	10.
	replacement rate of breeding stock	rate	[R/S]	11.
	weight of culls	weight	[R/S]	

size of animal crop	crop	[R/S]	12.
average net market weight	weight	[R/S]	13.
estimated price of culls	cull price	[R/S]	14.
estimated market price of animal feed requirements and costs	market price	[R/S]	15.
feed 1 quantity	quantity	[R/S]	16.
price	price	[R/S]	17.
feed 2 quantity	quantity	[R/S]	18.
price	price	[R/S]	19.
feed 3 quantity	quantity	[R/S]	20.
price	price	[R/S]	21.
feed 4 quantity	quantity	[R/S]	22.
price	price	[R/S]	23.
feed 5 quantity	quantity	[R/S]	24.
price	price	[R/S]	25.
TO OBTAIN A LIST OF VALUES			
If a print cradle is used		[INV] [2nd] [List]	0.
Enter 0			
End listing		[R/S]	

If a print cradle is not being used	[B]		1.00
Repeat until all memory registers are checked	[R/S]		pause
Correct an entry by following procedures in step 5			first value
Select program			memory register
Calculate necessary selling price of animal to cover total cost of feed and other variable costs (adjusted for value of wool and cull ewe; adjusted for value of cull cow)	[2nd] [Pgm] 14		pause
Calculate necessary selling price of animal to cover total cost of animals per animal unit (per litter in farrow-to-finish production)	[A]		next value
Calculate profit and return per animal (per litter in feeder-pig and farrow-to-finish production)	[B]		\$ VC (variable costs)
	[C]		\$ TC (total cost)
			Prof & Rt (profit and return)

<p>Calculate returns to labor and capital per animal unit (per litter in feeder-pig and farrow-to-finish production)</p> <p>Enter alternative crop and calculate necessary selling price to cover total costs with an alternative animal crop (number of hogs marketed in farrow-to-finish production)</p> <p>Enter weight and calculate necessary selling price of animals to cover total costs with an alternative marketing weight (calf-weaning weight for cow-calf production; pig-weaning weight for feeder-pig production)</p> <p>Calculate total feed cost</p> <p>Calculate other variable costs</p> <p>Calculate total fixed costs</p> <p>Calculate cull adjustment</p> <p>Calculate total adjusted variable cost</p> <p>Calculate adjusted total cost</p> <p>Calculate sales per unit (per litter in feeder-pig and farrow-to-finish production)</p>	<p>crop</p> <p>wt</p>	<p>[D]</p> <p>[E]</p> <p>[2nd] [E']</p> <p>[2nd] [A'] [R/S]</p> <p>[R/S]</p> <p>[R/S]</p> <p>[2nd] [B']</p> <p>[2nd] [C']</p> <p>[2nd] [D']</p>	<p>Ret/L & C (returns to labor and capital)</p> <p>alt. crop</p> <p>alt. wt</p> <p>feed cost</p> <p>variable costs</p> <p>fixed costs</p> <p>cull adjustment</p> <p>adj. VC</p> <p>adj. TC</p> <p>weight sold</p>
----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------	-----------------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------------	-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

<p>Calculate cull sold per unit (per litter in feeder-pig and farrow-to-finish production)</p> <p>Calculate total sales per unit (per litter in feeder-pig and farrow-to-finish production)</p> <p>Calculate production per unit (per litter in feeder-pig and farrow-to-finish production)</p> <p>Calculate gross income per unit including culls (per litter in feeder-pig and farrow-to-finish production)</p>		<p>[R/S]</p> <p>[R/S]</p> <p>[R/S]</p> <p>[R/S]</p>	<p>culls sold per unit</p> <p>total sales</p> <p>production per unit</p> <p>gross income</p>
-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------	--	-----------------------------------------------------	----------------------------------------------------------------------------------------------

CATTLE, PIG, OR LAMB FEEDING WORK SHEET

FM-15

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Clear memories		[2nd] [CMs]	0.
2	Select data entry and retrieval program		[2nd] [Pgm] 02	0.
	Enter pay weight of feeder	pay weight	[A]	2.
	Enter feeder price	feeder price	[R/S]	3.
	Enter annual interest rate	rate	[R/S]	4.
	Enter feeding period	feeding period	[R/S]	5.
	Enter labor cost	labor cost	[R/S]	6.
	Enter percent death loss of feeder cost	%	[R/S]	7.
	Enter marketing cost including hauling and commission	marketing cost	[R/S]	8.
	Enter operating and miscellaneous costs	operating cost	[R/S]	9.
	Enter fixed cost divided by turnaround rate	fixed cost	[R/S]	10.
	Enter net market weight	market weight	[R/S]	11.
	Enter estimated selling price	selling price	[R/S]	12.

Enter desired return to management and profit

Enter feed requirements & costs:

Feed 1, Quantity
Price

Feed 2, Quantity
Price

Feed 3, Quantity
Price

Feed 4, Quantity
Price

TO OBTAIN A LIST OF VALUES

If a print cradle is used

Enter 0

If no printer is used

return

quantity
price

quantity
price

quantity
price

quantity
price

0

[R/S]

[R/S]

[R/S]

[R/S]

[R/S]

[R/S]

[R/S]

[R/S]

[R/S]

[INV] [2nd] [List]

[B]

[R/S]

13.

14.

15.

16.

17.

18.

19.

20.

21.

0.

1.

pause

value stored in 01
memory

next memory number

pause

stored value

3a

3b

3c	Repeat this step until all memory registers are checked			
4	Correct errors by using the procedure for changing input in Step 5	[2nd] [Pgm] 15	[A]	\$/cwt VC
	Select program		[B]	\$/cwt TC
	Calculate selling price to cover cost of feeder, feed and other variable costs		[C]	Prof & RT
	Calculate selling price to cover cost of finishing animal		[D]	\$/cwt FDR
	Calculate profit and return to management per head		[R/S]	\$/hd FDR
	Calculate price that can be paid for feeder per cwt		[E]	\$/FD. 1
	Calculate price per head for feeder		[2nd] [A']	FDR cost
	Calculate price that can be paid for feed 1		[2nd] [B']	Feed cost
	Calculate feeder cost		[R/S]	\$/cwt
	Calculate total feed cost		[2nd] [C']	other VC
	Calculate cost per cwt of net gain		[R/S]	\$/day
	Calculate other variable costs		[R/S]	\$/hd
	Calculate nonfeed cost per day			
	Calculate fixed costs			

5	Calculate total cost to finished animal	[2nd] [D']	[R/S]	tot. cost
	Calculate total cost per cwt of net gain		[2nd] [E']	\$/cwt
	Calculate gross income		[STO] memory register number	gr. inc.
	TO CHANGE DATA VALUES		[INV] [2nd] [Fix]	value
	Enter desired data value			
	Remove the fixed decimal		[INV] [2nd] [Fix] [CLR] 4	
6a	Store data on magnetic cards		[2nd] [Write]	
6b	Insert card in bottom slot		[INV] [2nd] [Fix] [CLR] 4	
	Retrieve data on magnetic cards			
	Insert card in bottom slot			

LAND PURCHASE: FINANCIAL AND ECONOMIC ANALYSIS FM-16A

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Repartition memory (T1-58 only)	5	[2nd] [Op] 17	79.49
2	Select program		[2nd] [Pgm] 02	
	Store the following values: ^a			
	Interest rate	decimal rate	[A]	2.
	Number of repayment periods	number	[R/S]	3.
	Total number of acres in tract	acres	[R/S]	4.
	Sale price	price	[R/S]	5.
	Down payment rate	decimal rate	[R/S]	6.
	Proportion of principal to be repaid after final payment	decimal	[R/S]	7.
	If the net cash flow is to be calculated			
	Enter 0	0	[R/S]	8.
	Otherwise			
	Net cash flow	\$/acre	[R/S]	8.

<p>If the net cash flow has been entered in the previous step, enter 0 for the remaining data values in this step</p> <p>Debt repayment for added machinery and equipment investment</p> <p>Property taxes plus other land ownership costs</p> <p>Expected crop yield</p> <p>Expected price for crop</p> <p>Cost of seed, fertilizer, chemicals, crop insurance, and other crop costs</p> <p>Machinery fuel, lube, repair costs plus custom-hire costs</p> <p>Other cash costs of crop production</p> <p>Number of acres in each crop (if necessary, repeat the inputs corresponding to memories 10-15 for the second, third, and fourth crops raised, storing values in memory registers 20-25, 30-35, and 40-45, respectively)</p> <p>Outside cash flow per acre (+ or -)</p>	<p>\$/acre</p> <p>\$/acre</p> <p>bu/a or ton/a</p> <p>\$/bu or \$/ton</p> <p>\$/acre</p> <p>\$/acre</p> <p>\$/acre</p> <p>\$/acre</p> <p>\$/acre</p> <p>\$/acre</p> <p>\$/acre</p>	<p>[R/S]</p>	<p>9.</p> <p>10.</p> <p>11.</p> <p>12.</p> <p>13.</p> <p>14.</p> <p>15.</p> <p>16.</p> <p>17.</p>
----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------	------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------	-------------------------------------------------------------------------------------------------------------------------------------------------------------	---------------------------------------------------------------------------------------------------

TO OBTAIN A LIST OF VALUES

If a print cradle is used

Retrieve values in memories.

If a printer is not being used

Retrieve values in memories

3a

3b

Repeat this step until all memories have been checked

Correct an entry

Select program

If a net cash flow is stored in memory 07, the outputs may be found in any order; otherwise

Calculate the net cash flow

Store net cash flow in 07

Calculate loan amount to be borrowed

Calculate total loan payment each period

4

5

6

6a

6b

0

correct value

flow

[INV] [2nd] [List]

[B]

[R/S]

[STO] memory #
[2nd] [Pgm] 16

[2nd] [B']

[STO] 07

[A]

[B]

0.

1.

pause

first value

memory number

pause

next value

correct value

cash flow

cash flow

loan amount

payment

If payment plan requires level principal payments with interest on unpaid principal

Set flag

If payment plan requires level payments

Reset flag

Enter the payment number to be analyzed

Do not clear display

Do not clear display

Calculate maximum loan repayable

Calculate maximum price which can be paid for the land

Calculate number of periods needed to repay the loan

Remove the fixed decimal

7

[2nd] [St flg] 0

[INV] [2nd] [St flg] 0

[C]

[R/S]

[R/S]

[D]

[E]

[2nd] [A']

[INV] [2nd] [Fix]

N (number)

P (principal)

I (interest paid)

RP (principal remaining)

max. loan

max. \$

periods

*Zeros should be stored in memories not used

FARM LOAN ANALYSIS

FM-16B

STEP	PROCEDURE	ENTER	PRESS	DISPLAY
1	Select program			79.49
2	If using the TI-58, repartition memory		[2nd] [Pgm] 16 5 [2nd] [Op] 17	
3a	INSTALLMENT LOANS WITH EQUAL TOTAL OR EQUAL PRINCIPAL PAYMENTS Clear all memories		[2nd] [CMs]	
3b	Store interest rate per period*	interest rate	[STO] 01	interest rate
3c	Store number of payment periods	payment periods	[STO] 02	payment periods
3d	Store total principal due	principal	[STO] 04	principal
3e	If loan stipulates equal principal payments Set flag		[2nd] [St flg] 0	
3f	If loan stipulates equal payments Reset flag Enter the period number to be analyzed	N	[INV] [2nd] [St flg] 0 [C]	P (principal due)

3g	Do not clear display Do not clear display Analyze other periods by repeating steps d, e, and f Analyze loans with different terms by repeating steps a through f		[R/S] [R/S]	I (interest due) RP (principal remaining)
4a	SINGLE REPAYMENT LOAN Clear memories		[2nd] [CMs]	
4b	Store annual interest rate Store principal due	rate P	[STO] 01 [STO] 04	rate P
4c	If user knows the number of days in loan Store number of days Otherwise Store beginning date Store ending date Calculate total interest due	days month, day number month, day number	[STO] 05 [STO] 02 [STO] 03 [2nd] [E']	days month, day number month, day number total interest

4e

Calculate other single repayment loans by repeating steps a through e
Remove the fixed decimal

5

[INV] [2nd] [Fix]

*Zeros should be stored in memories not used

NOTES